# **NAME**

rgbds — object file format documentation

#### DESCRIPTION

This is the description of the object files used by rgbasm(1) and rgblink(1). *Please note that the specification is not stable yet.* RGBDS is still in active development, and some new features require adding more information to the object file, or modifying some fields, both of which break compatibility with older versions.

#### FILE STRUCTURE

The following types are used:

**LONG** is a 32-bit integer stored in little-endian format. **BYTE** is an 8-bit integer. **STRING** is a 0-terminated string of **BYTE**. Brackets after a type (e.g. **LONG**[n]) indicaten consecutive elements (here, **LONG**s). All items are contiguous, with no padding anywhere—this also means that they may not be aligned in the file!

**REPT** n indicates that the fields between the **REPT** and corresponding **ENDR** are repeated n times.

All IDs refer to objects within the file; for example, symbol ID \$0001 refers to the second symbol defined in *this* object file's **Symbols** array. The only exception is the **Source file info** nodes, whose IDs are backwards, i.e. source node ID \$0000 refers to the *last* node in the array, not the first one. References to other object files are made by imports (symbols), by name (sections), etc.—but never by ID.

#### Header

```
BYTE Magic[4]
```

"RGB9"

LONG RevisionNumber

The format's revision number this file uses. (This is always in the same place in all revisions.)

**LONG** NumberOfSymbols

How many symbols are defined in this object file.

**LONG** NumberOfSections

How many sections are defined in this object file.

# Source file info

LONG NumberOfNodes

The number of source context nodes contained in this file.

**REPT** NumberOfNodes

LONG ParentID

ID of the parent node, -1 meaning that this is the root node.

**Important**: the nodes are actually written in **reverse** order, meaning the node with ID 0 is the last one in the list!

LONG ParentLineNo

Line at which the parent node's context was exited; meaningless for the root node.

BYTE Type

# Value Meaning 0 REPT node 1 File node 2 Macro node

**IF** Type  $\neq 0$ 

If the node is not a REPT node...

# STRING Name

The node's name: either a file name, or the macro's name prefixes by its definition's file name (e.g. src/includes/defines.asm::error).

**ELSE** If the node is a REPT, it also contains the iteration counter of all parent REPTs.

```
\textbf{LONG} \ \textit{Depth}
```

LONG Iter[Depth]

The number of REPT iterations, by increasing depth.

ENDC

ENDR

#### **Symbols**

**REPT** NumberOfSymbols

**STRING** Name

This symbol's name. Local symbols are stored as their full name (Scope.symbol).

BYTE Type

# Value Meaning

- 0 **Local** symbol only used in this file.
- 1 **Import** of an exported symbol (by name) from another object file.
- 2 **Exported** symbol visible from other object files.

**IF** *Type* ≠ 1

If the symbol is defined in this object file...

LONG NodeID

Context in which the symbol was defined.

LONG LineNo

Line number in the context at which the symbol was defined.

LONG SectionID

The ID of the section in which the symbol is defined. If the symbol doesn't belong to any specific section (i.e. it's a constant), this field contains -1.

LONG Value

The symbol's value. If the symbol belongs to a section, this is the offset within that symbol's section.

**ENDC** 

ENDR

# **Sections**

**REPT** NumberOfSections

**STRING** Name

The section's name.

LONG Size

The section's size, in bytes.

BYTE Type

Bits 0–2 indicate the section's type:

Value	Meaning
0	WRAM(
1	VRAM
2	ROMX
3	ROM0
4	HRAM

- 5 WRAMX
- 6 SRAM
- 7 OAM

Bit 7 being set means that the section is a "union" (see "Unionized sections" in rgbasm(5)). Bit 6 being set means that the section is a "fragment" (see "Section fragments" inrgbasm(5)). These two bits are mutually exclusive.

#### LONG Address

Address this section must be placed at. This must either be valid for the section's Type (as affected by flags like -t or -d in rgblink(1)), or -1 to indicate that the linker should automatically decide (the section is "floating").

#### T.ONG Bank

ID of the bank this section must be placed in. This must either be valid for the section's *Type* (with the same caveats as for the *Address*), or -1 to indicate that the linker should automatically decide.

#### BYTE Alignment

How many bits of the section's address should be equal to AlignOfs, starting from the least-significant bit.

#### LONG AlignOfs

Alignment offset. Must be strictly less than 1 << Alignment.

# **IF** Type = 2 || Type = 3

If the section has ROM type, it contains data.

#### **BYTE** Data[Size]

The section's raw data. Bytes that will be patched over must be present, even though their contents will be overwritten.

#### LONG NumberOfPatches

How many patches must be applied to this section's Data.

#### **REPT** NumberOfPatches

#### LONG NodeID

Context in which the patch was defined.

# LONG LineNo

Line number in the context at which the patch was defined.

# LONG Offset

Offset within the section's *Data* at which the patch should be applied. Must not be greater than the section's *Size* minus the patch's size (see *Type* below).

# LONG PCSectionID

ID of the section in which PC is located. (This is usually the same section within which the patch is applied, except for e.g. LOAD blocks, see "RAM code" inrgbasm(5).)

#### LONG PCOffset

Offset of the PC symbol within the section designated by *PCSectionID*. It is expected that PC points to the instruction's first byte for instruction operands (i.e. jp @ must be an infinite loop), and to the patch's first byte otherwise (db, 'dw', 'dl').

# $\mathbf{BYTE} \ \mathit{Type}$

# Value Meaning 0 Single-byte patch 1 Little-endian two-byte patch

- 2 Little-endian four-byte patch
- Single-byte 'jr' patch; the patch's value will be subtracted to PC + 2 (i.e. jr @ must be the infinite loop 18 FE).

LONG RPNSize

Size of the *RPNExpr* below.

**BYTE** RPNExpr[RPNSize]

The patch's value, encoded as a RPN expression (seeRPN EXPRESSIONS).

ENDR

ENDC

# Assertions

LONG NumberOfAssertions

How many assertions this object file contains.

**REPT** NumberOfAssertions

Assertions are essentially patches with a message.

LONG NodeID

Context in which the assertions was defined.

LONG LineNo

Line number in the context at which the assertion was defined.

LONG Offset

Unused leftover from the patch structure.

LONG PCSectionID

ID of the section in which PC is located.

LONG PCOffset

Offset of the PC symbol within the section designated by PCSectionID.

BYTE Type

Describes what should happen if the expression evaluates to a non-zero value.

#### Value Meaning

- 0 Print a warning message, and continue linking normally.
- Print an error message, so linking will fail, but allow other assertions to be evaluated.
- 2 Print a fatal error message, and abort immediately.

LONG RPNSize

Size of the *RPNExpr* below.

**BYTE** RPNExpr[RPNSize]

The patch's value, encoded as a RPN expression (seeRPN EXPRESSIONS).

STRING Message

The message displayed if the expression evaluates to a non-zero value. If empty, a generic message is displayed instead.

**ENDR** 

#### RPN EXPRESSIONS

Expressions in the object file are stored as RPN, or "Reverse Polish Notation", which is a notation that allows computing arbitrary expressions with just a simple stack. For example, the expression 2 5 – will first push the value "2" to the stack, then "5". The '-' operator pops two arguments from the stack, subtracts them, and then pushes back the result ("3") on the stack. A well-formed RPN expression never tries to pop from an empty stack, and leaves exactly one value in it at the end.

RGBDS encodes RPN expressions as an array of **BYTE**s. The first byte encodes either an operator, or a literal, which consumes more **BYTE**s after it.

```
Value Meaning
$00
       Addition operator ('+')
$01
       Subtraction operator ('-')
$02
       Multiplication operator ('*')
       Division operator ('/')
$03
       Modulo operator ('%')
$04
$05
       Negation (unary '-')
$06
       Exponent operator ('**')
$10
       Bitwise OR operator ('|')
$11
       Bitwise AND operator ('&')
       Bitwise XOR operator ('^')
$12
$13
       Bitwise complement operator (unary '~')
$21
       Logical AND operator ('&&')
$22
       Logical OR operator ('| |')
$23
       Logical complement operator (unary '!')
       Equality operator ('==')
$30
$31
       Non-equality operator ('!=')
       Greater-than operator ('>')
$32
$33
       Less-than operator ('<')
$34
       Greater-than-or-equal operator ('>=')
       Less-than-or-equal operator ('<=')
$35
$40
       Left shift operator ('<<')
       Arithmetic/signed right shift operator ('>>')
$41
$42
       Logical/unsigned right shift operator (>>>)
$50
       BANK(symbol), followed by the symbol's LONG ID.
$51
       BANK(section), followed by the section's STRING name.
$52
       PC's BANK() (i.e.BANK(@)).
$53
       SIZEOF(section), followed by the section's STRING name.
       STARTOF(section), followed by the section's STRING name.
$54
       1dh check. Checks if the value is a valid 1dh operand (see "Load Instructions" in
$60
       gbz80(7)), i.e. that it is between either $00 and $FF, or $FF00 and $FFFF, both inclusive.
       The value is then ANDed with $00FF (& $FF).
       rst check. Checks if the value is a valid rst (see "RST vec" inqbz80(7)) v ector, that is
       one of $00, $08, $10, $18, $20, $28, $30, or $38. The value is then ORed with $C7 (
       $C7).
$80
       Integer literal. Followed by the LONG integer.
       A symbol's value. Followed by the symbol's LONG ID.
```

# SEE ALSO

```
rgbasm(1), rgblink(1), rgbds(7), gbz80(7)
```

# HISTORY

rgbds was originally written by Carsten Sørensen as part of the ASMotor package, and was later packaged in RGBDS by Justin Lloyd. It is now maintained by a number of contributors at https://github.com/gbdev/rgbds